Notes for **pydispersion** library All the library can be found at https:

//github.com/louislafforgue/pydispersion

Author: Louis Lafforgue louislafforg@gmail.com

Pulse implementation

All the class are stored in the file pulse.py

1.1 Analytical pulse

```
Analytics(shape="Gaussian", w0=2, E0=1, FWHM=10, poly_phase=[0] ,repre="time",N_grid=2**15, N_signal=2**11, **kwargs)
```

Creation of a pulse object from an analytical expression either from temporal or frequencial representation, the different parameters and pulse representation are implemented thanks to a Fourier transform

- shape: "Gaussian", "Hsech", "Lorentzian", default: "Gaussian"
- repre: "time" or "freq", parameters given for the time representation of the pulse id repre="time", for the spectral representation if repre="freq".
- $w\theta$: float, ω_0 of the pulse in rad/fem, default 2
- E0: float, Maximum amplitude in arbitrary unit, default 1
- FWHM: float, FWHM of the pulse depending of the representation.
- $poly_phase$: poly_phase= list(float) , list with the polynomial coeffecients, ex: [1,2.3,5] = 1+2.3t+5t^2
- N_{-qrid}: int, size for the Fourier transform grif, more efficient as a power of two
- \bullet N_{-grid}: int, size for the discretized signal, more efficient as a power of two

1.2 Data input pulse

Data_input(file_name,phase=[], axex="lambda", smoothing=True, **kwargs)

Creation of a pulse object from .dat or .csv file the file has to be given as following first column: frequency, second column: Intensity amplitude

- file_name: string (), file name with the extension, example: "pulse.dat"
- phase: np.array, phase array, default, null phase
- axex: unit for the X-axis in the file, "lambda": wavelength in nm, "freq": frequency in 10**15 Hz, "omega" angular frequency in rad/fs
- *smoothing*: bool, True to apply a smoothing to the experimental spectrum (recommended for the calculations)

1.3 Common methods in class $Data_input$ and Analytics

GetParameters(X,Y,precision=1.e-2)

Calculate the parameters X at Y-maximum , Y-maximum, and FWHM for a given profile. Return 3 floats.

- X: np.array, X axis
- Y: np.array, Y profile
- precision: optional, float, precision for the FWHM calculation
- SetParameters(precision=1.e-2)

Calculate and update the frequency parameters of the pulse, ω_0 , Field maximum amplitude E_0 and frequency FWHM

- precision: optional, float, precision for the FWHM calculation
- SetTimeParameters(precision=1.e-2)

Calculate and update the temporal parameters of the pulse, the delay, Field maximum amplitude E_0 and time FWHM (or half maximum duration) Store them in the dict parameters as 'w0': ..., 'E0_t': ..., 'HMD': ...

- precision: optional, float, precision for the FWHM calculation
- FreqtoTime(update=True)

Compute the inverse Fourier transform of the pulse

• update: optional, bool, True to have the result updated in the pulse object

1 TimetoFreq(update=True)

Compute the Fourier transform of the pulse

• update: optional, bool, True to have the result updated in the pulse object

Save(file_name)

Save the pulse in a .dat file

• file_name: String, file name

1 Copy()

Copy the pulse and return a pulse object

Components implementation

All the class are stored in the file *components.py*

2.1 Matter

Matter(name)

Implement an object which corresponds to a transparent medium characterized by a refractive index $n(\lambda)$

• name : str() , matter name, all the matter already implemented can be printed with *Matter.media*

If you want to use a media not implemented, either implement or initialize with a random medium and change the configuration after the implementation using the representation of the Sellmeier equation:

$$n^{2}(\lambda) = A + \sum_{i} \frac{B_{i}\lambda^{2}}{\lambda^{2} - C_{i}}$$

medium.indice=[A,[B1,C1],[B2,C2]...]

```
medium=Matter("BK7") #initialized the object
medium.name="new medium"
```

Methods

propagation(z,pulse_in, third_order=False)

Compute the propagation in the medium for a given distance z, return a pulse object corresponding to the pulse after the propagation

- z: float, distance of propagation in micrometre
- pulse_in: pulse object, initial optical pulse before the medium

• third_order: bool, consider True or not the third-order propagation, default=False

calculate_indice(1)

return the numerical value of the refractive index for a given wavelength

 \bullet l: float, wavelength in micrometre

derivatives(1)

return the numerical value of the different orders of the Taylor-development of k (k_0, k'_0, GVD, TOD) , for a given wavelength

 \bullet l: float, wavelength in micrometre

2.2 Double Grating Compressor

Class GratingCompressor




Figure 2.1: Double parallel grating compressor

GratingCompressor(d)

Implement the object

• d: float, grating density in 1/micrometre

Methods

propagation(pulse_in, gamma, z)

Return a pulse object after the grating compressor

- pulse_in: pulse object, initial optical pulse
- gamma: float, incidence angle (see figure)
- z: float, distance in between the 2 gratings (see figure)

GDDcalculate(10, gamma, z)

Return a numerical value of the grating compressor GDD

- l0: float, central wavelength in micrometre
- gamma: float, incidence angle (see figure)
- z: float, distance in between the 2 gratings (see figure)

2.3 Double Prism Compressor

Class DoublePrismCompressor




Figure 2.2: Double parallel prism compressor

DoublePrismCompressor(alpha=pi/3, matter_name="SiO2", Brewster=False)

Implement the object

- alpha: float, apex angle in radian
- \bullet matter_name: matter name of the prism, matter available with Matter.media, to change the media follow the steps presented in the class matter
- Brewster: bool, True to be in the brewster angle configuration

Methods

```
propagation(pulse_in, 11, w, h, gamma1=0)
```

Return a pulse object after the prism compressor

- pulse_in : pulse object, inital optical pulse
- 11 : float, x distance entrance-apex in micrometre (see figure)
- w: float, x apex-apex distance in micrometre (see figure)
- h: float, y apex-apex distance in micrometre (see figure)
- gamma1: float, incidence angle in radian(see figure)

GDDcalculate(10, 11, w, h, gamma1=0)

Return a numerical value of the prism compressor GDD

- \bullet l0: float, central wavelength in micrometre
- 11: float, x distance entrance-apex in micrometre (see figure)
- w: float, x apex-apex distance in micrometre (see figure)
- h: float, y apex-apex distance in micrometre (see figure)
- gamma1 : float, incidence angle in radian(see figure)

Graphic

All the class and methods are stored in file graphic.py

BaseGraph(title):

Implement the graph object

 \bullet title: optional str, plot title

Methods

comparedouble(pulse1, pulse2)

Plot the frequency and the temporal representation of two pulses in the same window, the result is presented in the section example

- pulse1: pulse object, pulse to plot
- pulse2: pulse object, pulse to plot

```
compare(pulse1, pulse2)
```

Plot the frequency and the temporal representation of two pulses in different windows, the result is presented in the section example

- pulse1: pulse object, pulse to plot
- pulse2: pulse object, pulse to plot

```
plotattribut(pulse, X="X", Y="Y", legend_X="frequency 10^15 rad/s", legend_Y
="Field amplitude a.u",label="", absolute=False, **kwargs)
```

Plot an attribute of a pulse. List of the possible attributes to plot are

X	frequency absice in 10^{15} rad/s
Y	frequency amplitude in a.u
phase	spectral phase in rad
$X_{-}time$	Time abscisse in fs
Y_time	Time amplitude in a.u
temporal_phase	temporal phase in rad

• pulse : pulse object, pulse to plot

ullet Y: np.array, Y-axis of the plot

 \bullet $legend_X$: string, legend for X-axis

 $\bullet \ legend_-Y$: string, legend for Y-axis

ullet absolute: bool, True to take the absolute value of the signal

Examples

```
pulse_in=pulse.Data_input("test.dat", axex="lambda")
pulse_in.SetParameters() #calculation of frequency parameters
pulse_in.SetTimeParameters() #calculation of temporal parameters

glass=components.Matter('SiO2') # creation of the material

pulse_out=glass.propagation(10000, pulse1) # propagation after 1 mm, z is given in micrometres
pulse_out.SetParameters() # calculation of the paramaters
pulse_out.SetTimeParameters()

graphique=graphic.BaseGraph()
graphique=graphic.BaseGraph()
graphique.comparedouble(pulse_in, pulse_out) #ploting the results
```

Listing 4.1: pulse from data input propagation




Figure 4.1: result window for the method *comparedouble*, propagation of an experimental pulse after 1000 of SiO2

Listing 4.2: Analytical pulse propagation




Figure 4.2: result window for the method $\it compare$, propagation of a gaussian pulse in 0.5mm of BK7 glass